



Version 5.01

## UPGRADE INSTALLATION PROCEDURES

SIS-TECH Applications is thankful for your interest in SIL Solver®. **We are proud to provide you with the new SIL Solver® Version 5.01!**

### INSTALLATION INSTRUCTIONS


1. This upgrade involved an executable file. You must first determine that you have permission to open and run EXE files. Many IT departments limit your capability to open and/or save EXE files to your PC. If you do not have ADMIN rights to your computer, consult with your IT department. **This upgrade will only work if you have a previously installed copy of SIL Solver® using a SIL Solver® installation CD and you have rights to install software on your PC.**
  
2. When you are ready to upgrade SIL Solver®, close all applications, including SIL Solver® and any other application that is not being used as part of installing the upgrade. **This upgrade creates a new root directory on your PC called SILupdate. The SILupdate will self-launch from this folder to update the “Silsolver” folder in the location that you select in Step 5. It is not writing any files to directories other than the folders “SILupdate” and “Silsolver”.**
  
3. Run file named silupdate\_SIL.exe
  
4. The WinZip Self-Extractor will launch. This may take a few minutes to extract the file depending on the speed of the connection. If you hit any button during the installation, you will be prompted with a selection to cancel or continue with installation.
  
5. After the Self-Extractor is complete, you will see the screen shown in Figure 1. On some Microsoft Windows systems, this screen may be minimized (especially if you do not close all applications as suggested in Step 2.). If minimized, simply select the SIL Solver® button on the Windows toolbar.
  - A. Make changes to the default settings, if necessary.
  - B. When you pick **Select Location**, the software will default to the **SILUpdate** folder that the update program has created under the root directory for use during installation. You must browse to select the location of the **Silsolver** folder. The default installation location for SIL Solver® is the **Program Files** directory. Once you have selected the



location, the upgrade will proceed. Do not select **Close** unless you intend to stop installation. The upgrade may take a few minutes, dependent on your system.

List upgrades in this release. You do not have option to deselect.

You have the option to select to **Replace all device sheets** or **Replace default device sheets only**. If you have built your own database in SIL Solver, select **Replace default device sheets only**.



Select location of the **Silsolver** folder. **DO NOT** perform this step until you have confirmed what upgrades you want to select. See text box on left.

Figure 1. Allows configuration of your upgrade installation

6. After you have completed your selections in Step 5, the installation will proceed and when finished it will display the message shown in Figure 2.



Figure 2. Final Screen